



Model 90 Switcher

Documentation for the Model 90 Switcher is currently being created. When complete, a .PDF file will be available for download on the Studio Technologies website at www.studio-tech.com.

The enclosed CD contains the Model 90's application program. The installation program should run automatically. The application program allows the Model 90 to be controlled via a USB connection.

Also included on the CD are two files required by SIA Software's SmaartLive 5™ for supporting the Model 90. (These files are required in addition to the appropriate version of SmaartLive 5.) On the CD they are located in the \SIA Drivers folder and are named Model90.dll and model90.ssw. They should be copied and stored in a folder named "\switchers" created in the main SIA Software folder.

Note that it can be confusing to find these files on the CD due to the automatic installation feature. To access the files is actually simple, but a bit convoluted. Start by inserting the CD into the drive. When the installation program starts use the cancel button to terminate the installation. Then use Windows® Explorer to highlight the CD in the CD drive. Now right click the mouse button and use the Explore command to view the files and folders on the CD. Select the \SIA Drivers folder to view the two files that need to be copied.

**STUDIO
TECHNOLOGIES
INC.**

5520 West Touhy Avenue
Skokie, Illinois 60077 USA
Telephone 847-676-9177
www.studio-tech.com